



Upgrade OTCnet Offline Check Capture Software

The term '*install*' refers to a situation in which the OTCnet Offline application was not previously installed. The term '*upgrade*' refers to a situation in which the OTCnet Offline application was previously installed and an updated version is being applied.



Application Tip

Before initiating an Offline Check Capture software upgrade, consider the following information:


- You need Windows Administrator privileges for each computer you will be upgrading.
- If you are upgrading to a newer OTCnet Offline version, you must uninstall the previous offline version and then perform a new installation.
- If you are upgrading OTCnet Offline, you must install the application first, **before** creating the CCA Offline logon profile. You also need to create a CCA Offline logon profile to run the OTCnet Offline application, but it can only be created **after** installing the OTCnet Offline application. Refer to the *Create a Check Capture Administrator Offline Logon Profile* printable job aid.
- If you are upgrading OTCnet Offline, and your Agency manages verification records, you do not need to reset and download the Local Verification Database (LVD) for each terminal.
- More than one OTCnet Offline application environment (Production or QA) can be installed and upgraded on a computer. Each Offline application environment must be upgraded separately.

To upgrade OTCnet Offline Check Capture software, complete the following steps:

1. Close open batches and upload all existing batches in Batch Management.

2. Stop the Offline application. From the Windows Start Button menu, select **Stop OTCnet Offline**.

Figure 28: Stop OTCnet Offline




3. Locate the folder where the OTCnet software file (EXE file) resides, and double-click the OTCnet Offline.exe icon.

Figure 29: OTCnet Offline.exe Icon




4. The *Welcome to the OTCnet Offline Installation Wizard* dialog box appears. Click **Next**.

Figure 30: OTCnet Offline Installation Wizard




5. The *Destination Location* dialog box appears. Click **Next**.

**Application Tip**


To install the software to another folder destination, click Browse to select a different folder. Click Cancel to exit the setup.

Figure 31: Destination Location




6. The *Start Installation* dialog box appears. Click **Next**.

Figure 32: Start Installation



7. The *CCA Offline User Credentials* dialog box appears. Enter your **Enter ID** and **Offline Password** in the appropriate text boxes, and click **Next**.


Figure 33: CCA Offline User Credentials

The image shows a Windows-style dialog box titled "CCA Offline User Credentials". The main area contains the text "Enter CCA User ID and Offline Password" next to a CD-ROM icon. Below this are two text input fields: "User ID:" and "Offline Password:". At the bottom left, it says "Wise Installation Wizard®". At the bottom right, there are two buttons: "Next >" (highlighted with a red rectangle) and "Cancel".

Application Tip

If an incorrect **User ID** and/or **Offline Password** is entered, an *Installation Error* dialog box message appears stating that the entered username (User ID) and/or password is invalid. Click **OK**. The upgrade process will be cancelled. As a result, you will need to run the installer again, and enter the correct credentials.

Figure 34: Installation Error



8. Wait while the files install. After the *OTCnet Offline has been successfully installed* message appears, click **Finish**.

Figure 35: OTCnet Offline has been successfully installed

